

# Startup Properties

During the startup sequence of MapTool several properties can be defined on different places. This guide tries to make it a little bit more clear, which can be set where and how.

## Definitions of Startup Properties

Startup Properties are properties, you can set only during the startup phase of the application. If you change same, you have to restart the application. There are several reasons for this behavior:

- JVM property: They are for the java virtual machine in where the application is running. Best examples are the memory properties to define the memory usage of the JVM.
- Only on startup relevant: E.g. which campaign is loaded during startup is only relevant during startup
- Complicate to change later: E.g. changing the location of files (e.g. MAPTOOL\_DATADIR) during a session is complicated and normally not necessary.

## Locations To Set Values

First of all, try to use the startup tab on the option window in the maptool UI. The application will try to save your changes in the correct location. But not all settings are changeable over the UI and if the UI tells you, to do the change by yourself, it is god to know some backgrounds.

You can set the value of a property on several locations. Since there are no guaranties, that the value of a property is set on only one location or that it has the same value on all locations, there is a clear hierarchy for the priority of a location.

The locations and there priority from high (overwrite) to low (will be overwritten) by higher locations first:

- **MapTool Command Line Option**
  - When you start the MapTool application, you can start it with optional parameters
  - With -h you can get a list of the current command line options of MapTool

- E.g. `maptool.exe -D="data dictionary"` to tell MapTool where the data dictionary is (should be)
- **Startup Property File**
  - The standard location & name of this file is `startup.properties` in the `config` subdirectory of the data dictionary of MapTool. E.g. `{user.home}/.maptool/config/startup.properties`
  - There is an `startupExample.properties` file with instructions and a list of the currently supported properties at the default location
  - A property is a key value text pair with a '=' or ':' between them
  - E.g. `MAPTOOL_DATADIR="data dictionary"`
- **JVM Command Line Parameters (-D, -X, ...)**
  - *Correct usage (prefix) unknown*
  - Normally you can set the properties from the configuration file (`MapTool.cfg`) also during the call of the JVM
  - You can see the normal, not usable prefix in the `MapTool.cfg` file, e.g. `-DMAPTOOL_DATADIR="data directory"`
  - MapTool use a launcher to start the JVM so there should be a prefix you have to set before the JVM option
  - This location should only be used if the application has problems to experiment with different setups.
  - *Note: with -D parameters you can declare and set system properties*
- **MapTool.cfg (-D, -X, ...)**
  - The configuration file of MapTool is in the `app` subdirectory of the application home directory, e.g. `{application home}/app/MapTool.cfg`
  - This file is overwritten during an update and holds user specific parameters and inherent application specific parameters together
  - Use the startup property file for user specific parameters
  - This location should only be used if the application has problems to change general setups of the application.
  - *Note: with -D parameters you can declare and set system properties*
- **Default System Properties**
  - Most default system properties are dependent values from the operating system (OS) and are set by the JVM
  - e.g. `user.home` get at the value the path&name of the OS specific home directory of the current user in the OS who starts the application
  - The non standrd system properties will get there default value from the application
- **Default Values**
  - This values are defined inside the MapTool application to define a fallback value, if needed.

## Property Overview

This table should give you an overview about all properties during the startup process.

KEY	Default Value	System	Startup	Command Line		Set By	Description
				short	long		
os.name	os dependent						Name of the operating system
user.home	os dependent						Home directory of the os user
MAPTOOL_DATADIR	.maptool	+	(+)	D	datadir	user	Main directory for runtime data (under user home) Will be ignored in Startup, if MAPTOOL_STARTUP_FILE is relative to the data directory.
MAPTOOL_LOGDIR	logs	+	+			user	Directory for logging data (under datadir)
CONFIG_SUBDIR_NAME	config						Subdirectory under datadir for configuration data
TEMP_SUBDIR_NAME	tmp						Subdirectory under datadir for temporary data
CMD_OPTIONS_HELP				h	help	user	Command options incl. description to log and information frame
DEBUG_FLAG	false (not set)			d	debug	adv.	Set log level to debug and turn on system.out enhanced debug output
VERSION_OVERWRITE	current version			v	version	dev.	Overwrites the MapTool version. <b>ONLY FOR DEVELOPMENT.</b> Some MapTool functions will break if the version is not set correct! This can corrupt your data!
FULLSCREEN_FLAG	false (not set)		+	f	fullscreen	user	Maximize the MapTool window on startup
MONITOR_TO_USE	-1 (not overwrite)			g	monitor	adv.	Sets which monitor (graphical device) to use.
WINDOW_WIDTH	-1 (not overwrite)			w	width	adv.	Override MapTool window width. Only usable together with monitor and height
WINDOW_HEIGHT	-1 (not overwrite)			h	height	adv.	Override MapTool window height. Only usable together with monitor and width
WINDOW_XPOS	-1 (not overwrite)			x	xpos	adv.	Override MapTool window starting x coordinate. Only usable together with monitor and ypos
WINDOW_YPOS	-1 (not overwrite)			y	ypos	adv.	Override MapTool window starting y coordinate. Only usable together with monitor and xpos
LIST_MACRO_FLAG	false (not set)			m	macros	adv.	Writes a list of the defined macro functions into the log

KEY	Default Value	System	Startup	Command Line		Set By	Description
				short	long		
RESET_FLAG	false (not set)			r	reset	adv.	Reset startup options to defaults
DEPRECATED_LOAD_CAMPAIGN_NAME				F	file		Load campaign from file on startup. Deprecated: Please use C or campaign
LOAD_CAMPAIGN_NAME			+	C	campaign	user	Load campaign on startup. Arg.: Full file path and name of the campaign
MAPTOOL_STARTUP_FILE	startup.properties under config dir.			P	startup-file	user	Override name (& path) of the startup properties file
SKIP_AUTO_UPDATE_FLAG	false (not set)		+			user	Skips the auto update process. There is also a user preference to do this.
LOCALE_LANGUAGE	default from OS	+	+			user	Sets the (default) language for the MapTool UI. Fallback will be en (English).
LOCALE_COUNTRY	default from oOS	+	+			user	Sets the (default) country for the MapTool UI.
MAX_MEM		+				adv.	
MIN_MEM		+				adv.	
STACK_SIZE		+				adv.	
ASSERTION		+				adv.	
JAVA2D_D3D		+				adv.	
JAVA2D_OPENGL_OPTION		+				adv.	
MACOSX_EMBEDDED_OPTION		+				adv.	

## Legend / Notes

Legend	Description
KEY	identification of the value
Default Value	The value, which is used if the value of the key is not set explicitly
System	Can be set in the MapTool.cfg or by the JVM command line parameters, if there is a + in the key row
Startup	Can be set in the startup properties file, if there is a + in the key row. (+) has side conditions, see description in the row of the key
Command Line Short	A single letter to use with a '-' as prefix in the command line of the application call to select the key
Command Line Long	A single word to use with a '-' as prefix in the command line of the application call to select the key

<b>Legend</b>	<b>Description</b>
Set By	Normally set by a normal user (user) or an advanced user (adv.) or a developer (dev.)
Description	Description to the key meaning and usage
<b>Note for</b>	<b>Note</b>
Keys ending with FLAG	This keys have a boolean value, true or false. There default value is false and if they are set somewhere, they will be true, no matter what value was used to set the key. (E.g. If you set SKIP_AUTO_UPDATE_FLAG="false" the value will be true!!! It can never be set back to false) Command line has no argument. (E.g. -f or -fullscreen and not -f="true")

## Recommendation

First try to change the values over the startup tab on the option window. On some OS the MapTool.cfg file is not writeable, so you can not change everything what you can see.

Specially the command line options have to be set directly by yourself.

If you need your own dictionary location(s), best practice would be to set the -P command line option to tell MapTool, what the path & name of the startup property file is and define anything else in that file.

(The data dictionary directory can only be set in the startup properties file, if the startup properties file will be located independent from the data dictionary!)

If your MapTool application seems to be instable and your OS does not allow the setting of new values over the startup tab on the option window, then go and try to manipulate the MapTool.cfg file.

Try to avoid changes in the MapTool.cfg file, because the file will be overwritten by the next update.

## State

### Under Construction

For MapTool Version 1.12.x (under development)

From:  
<http://wiki.dev.rainer-muetze.de/> - **Snarfburs Development Wiki**

Permanent link:  
<http://wiki.dev.rainer-muetze.de/project:mt:ug:stratupprops?rev=1681235521>

Last update: **2023/04/11 19:52**

